

EPFC 19.12.6 - P6 EPPM Connect

Download and Install client

URL: https://p6epfc-v19.emerald-associates.com/





Click over "P6 Client v19.12.6" and save the file




Right-click over the download file and select "Extract All..."

Define a folder and client "extract"






Go to the folder where it was extracted and double-click "setup.exe"



Remove checkmark from "Replace existing data" if checked.

Choose Advanced install.



If you click over "Primavera P6 Professional (x64)", it will allow you to change the "Install Location".


Click Next.



Click Install.

Remove all checkmarks.

Click OK.





Configuring database connection

Database connections

	А	В
1	EPFC	
2	Database Alias	EPFC
3	Dirver Type	P6 Pro Cloud Connect
4	Database (*)	EPFC
5	URL	https://p6epfc-v19.emerald-associates.com/p6procloudconnect/
6	Read Timeout	9999
7	Use SAML SSO	Disabled
8	Enable Client-side Cache	Disabled
9		
10	EPFC-DEV	
11	Database Alias	EPFC-DEV
12	Dirver Type	P6 Pro Cloud Connect
13	Database (*)	EPFC-DEV
14	URL	https://p6epfc-v19.emerald-associates.com/p6procloudconnect/
15	Read Timeout	9999
16	Use SAML SSO	Disabled
17	Enable Client-side Cache	Disabled
18		

CREATING THE CONNECTIONS







Click "Next"

Select "Create a new database alias"

Click "Next"





Define the "Database Alias"


Select "Driver Type" as "P6 Pro Cloud Connect"


Use the informations provided on & Database connections

Click "Next"

Use the informations provided on ♣ Database connections

Click "Next"







Click "Finish".

Repeat the procedure to add the other databases.

Running P6

Click on the Windows icon and select search for "P6 Professional 19 (x64)".





Enter username and password.

Select the database;

Click Connect

